

Wikiprint Book

Title: 1. TGCC presentation

Subject: Igcmg_doc - Doc/ComputingCenters/TGCC

Version: 77

Date: 06/29/24 08:35:03

Table of Content


| | |
|---|----------|
| Working on TGCC | 3 |
| 1. TGCC presentation | 3 |
| 2. TGCC's machines and file systems | 3 |
| 3. How to install your environment on TGCC | 3 |
| 4. Project and computing needs | 4 |
| 5. About file systems | 4 |
| 5.1. Quotas | 4 |
| 5.2. CCCSCRATCHDIR | 4 |
| 5.3. CCCWORKDIR | 4 |
| 5.4. CCCSTOREDIR | 4 |
| 5.5. ccc_home command to know directory complete pathname | 4 |
| 5.6. Storage spaces available from ESGF/THREDDS | 5 |
| 6. Specific directories for projects | 5 |
| 7. Specific file systems for CMIP6 | 5 |
| 7.1. GENCMIP6_HOME | 5 |
| 7.2. GENCMIP6_CCCWORKDIR | 6 |
| 7.3. GENCMIP6_CCCSTOREDIR | 6 |
| 7.4. GENCMIP6_SCRATCHDIR | 6 |
| 8. End-of-job messages | 6 |
| 9. Simulation outputs | 6 |
| 10. About password | 6 |
| 11. The TGCC's machines | 6 |
| 11.1. Irene | 6 |

Working on TGCC

1. TGCC presentation

■ <http://www-hpc.cea.fr/en/complexe/tgcc.htm>

2. TGCC's machines and file systems



3. How to install your environment on TGCC

- More information on the open-access website: ■ <http://www-hpc.cea.fr/en/complexe/tgcc.htm>
Online access to the machines' users manual (you will need a TGCC login and password): ■ <https://www-tgcc.ccc.cea.fr/> .
- Online access to technical issues and news : ■ <https://www-tgcc.ccc.cea.fr/en/news/index.html>
- TGCC's machine is [Irene](#) (Bull Skylake)
- Note: the **\$HOME/snapshot** directory contains hourly, daily, and weekly backups of your \$HOME files.

It is important to take the time to install a comfortable and efficient environment.

We suggest the user to use the igcmg environment (in bash) with a copy of the bashrc in his HOME.

```
ryyy999@irene: cp /ccc/cont003/home/igcmg/igcmg/MachineEnvironment/irene/bashrc ~/.bashrc
```

Additionally, you can copy and complete the example of bashrc_irene file to create your favorite environment (alias, module load ...). Don't forget to use it in .bashrc.

```
ryyy999@irene: cp /ccc/cont003/home/igcmg/igcmg/MachineEnvironment/irene/bashrc_irene ~/.bashrc_irene
ryyy999@irene: vi ~/.bashrc # to point your own .bashrc_irene
```

WARNING : if you have a ~/.profile file, it's better to remove it to avoid any problem during the execution of a simulation with libGCM

In this environment is specified:

the path to the compiler tool fcm and to the rebuild tool which recombines output files from a parallel model:

```
export PATH=$(ccc_home -u igcmg)/Tools/fcm/bin:$(ccc_home -u igcmg)/Tools/irene/bin:$PATH
```

- the load of modules giving access to computing or post processing libraries and tools needed on our platform (done in ccc_home -u igcmg/MachineEnvironment/irene/env_atlas_irene).

4. Project and computing needs

- To find out the computing time used by the projects you are involved in (daily update):

```
ryyy999@irene: ccc_myproject
```

- When you will create a job you need to specify in the header the project from which you will use computing time:

```
#MSUB -A genxxx
```

5. About file systems

5.1. Quotas

To check the available and used storage capacities of HOME, CCCSCRATCHDIR, CCCWORKDIR and CCCSTOREDIR:

```
ryyy999@irene: ccc_quota
```

On the Irene machine this command will also return the space used by scratch (a specificity of the Irene machine).

This command has been improved and gives a lot of information : quotas and usage of shared space, type and duration of exception.

5.2. CCCSCRATCHDIR

The `CCCSCRATCHDIR` directory is often cleaned and only files that are less than 40 days are stored.

5.3. CCCWORKDIR

The `CCCWORKDIR` directory corresponds to the `$WORKDIR` directory on Irene. It is large but its content is not backed up. Don't forget to do a backup (tar) for important directories.

5.4. CCCSTOREDIR

To manipulate the files in `/ccc/store` a few commands are useful:

```
# Demigrate a list of files on CCCSTOREDIR, see also "ccc_hsm -h"
ccc_hsm get $CCCSTOREDIR/FILE1 $CCCSTOREDIR/FILE2 ...

# Demigrate recursively the files from a CCCSTOREDIR directory, see also "ccc_hsm -h"
ccc_hsm get -r $CCCSTOREDIR/DIRECTORY

# Find out the used space on CCCSTOREDIR
cd $CCCSTOREDIR ; find . -printf "%y %s %p \n" | \
    awk '{ SUM+=$2 } END {print "SUM " SUM/1000000 " Mo " SUM/1000000000 " Go" }'

# or use --apparent-size with du :
du -sh --apparent-size
```

5.5. ccc_home command to know directory complete pathname

`ccc_home` could help you to find directory complete pathname for an other user or for you .

```
>ccc_home -h
ccc_home: Print the path of a user directory (default: home directory).
usage: ccc_home [ -H | -s | -t | -W | -x | -A | -a | -n ] [-u user] [-d datadir]
           [-h, --help]
```

```

-H, --home           : (default) print the home directory path ($HOME)
-s, -t, --cccscratch : print the CCC scratch directory path ($CCCSCRATCHDIR)
-X, --ccchome       : print the CCC nfs directory path ($CCCHOMEDIR)
-W, --cccwork       : print the CCC work directory path ($CCCWORKDIR)
-A, --cccstore      : print the CCC store directory path ($CCCSTOREDIR)
-a, --all           : print all paths
-u user             : show paths for the specified user instead of the current user
-d datadir          : show paths for the specified datadir
-n, --no-env        : do not load user env to report paths
-h, --help          : display this help and exit

> ccc_home -A -u ryyy999
/ccc/store/cont003/genXXX/ryyy999

```

5.6. Storage spaces available from ESGF/THREDDS

To store a file for the first time on esgf/thredds, you must ask for esgf/thredds write access by mail to the TGCC hotline access :
hotline.tgcc@cea.fr.

```

On Irene :
/ccc/work/cont003/dods/public/login
/ccc/store/cont003/dods/public/login

On a server web : store or work
https://vesg.ipsl.upmc.fr/thredds/catalog/catalog.html

```

6. Specific directories for projects

Since June 2018 3 differents directories are available for each project. More information soon.

7. Specific file systems for CMIP6

For gencmip6 project, and only for it, 3 more file systems and 4 more directories are available. Phase 1 have been installed in april 2016. Phase 2 and Phase 3 will come later in 2017 and 2018.

To use them, in interactive mode, you have to do : `module load datadir/gencmip6`.

Since libGCM_v2.8.1, if you set your project to gencmip6/devcmip6, they are automatically used in place of usual HOME, CCCWORKDIR, CCCSTOREDIR and SCRATCHDIR : `module switch dfldatadir dfldatadir/gencmip6` called from libGCM.

7.1. GENCMIP6_HOME

- 50 TB
- gencmip6 group quota
- dedicated to sources and scripts
- strongly recommended for CMIP6 sources and simulations scripts
- regular snapshot are taken by the system. See \$GENCMIP6_HOME/.snapshot Attention : you need an interactive connexion on a compute node :

```

> ccc_mprun -s -p standard -A devcmip6 -T 1800 -Q test
> cd
> . .bash_login
> cd .snapshot
> ls -l
total 44
drwxr-sr-x. 13 xxx gencmip6 4096 Dec 17 09:47 daily.2017-02-07_0010
drwxr-sr-x. 13 xxx gencmip6 4096 Dec 17 09:47 daily.2017-02-08_0010
...

```

7.2. GENCMIP6_CCCWORKDIR

- 2.5 PB in phase 1, 5 PB in phase 2
- gencmip6 group quota
- dedicated to small output files (ATLAS, MONITORING)
- available through <https://esgf.extra.cea.fr> following work_thredds
- no backup

7.3. GENCMIP6_CCCSTOREDIR

- 2.5 PB in phase 1, 5 PB in phase 2 and 14 PB on tape in phase 3
- gencmip6 group quota
- dedicated to large (more than 1GB) output files (Output, Analyse)
- available through <https://esgf.extra.cea.fr> following store_thredds
- linked with HSM (tapes)

7.4. GENCMIP6_SCRATCHDIR

- same file system as GENCMIP6_CCCWORKDIR
- used during batch execution (RUN_DIR) and erased at the end of the execution
- regular cleaning after 40 days

8. End-of-job messages

To receive the end-of-job messages sent by the job itself: end of simulation, error,... you must specify your address in the \$HOME/.forward file.

News in June 2018 : On Irene you have to duplicate a .forward for each project HOME.

9. Simulation outputs

Final simulation outputs are stored in \$CCCSTOREDIR/IGCM_OUT and on \$CCCWORKDIR/IGCM_OUT regarding the ATLAS and MONITORING directories.

The esgf/thredd server on TGCC are available via:

- <https://vesg.ipsl.upmc.fr/thredds/catalog/catalog.html>, click on store, click on your login or directly : <https://vesg.ipsl.upmc.fr/thredds/catalog/store/YOURLOGIN/catalog.html> and ATM (or an other component) for Analyse files (TS or SE)
- <https://vesg.ipsl.upmc.fr/thredds/catalog/catalog.html>, click on work, click on your login or directly : <https://vesg.ipsl.upmc.fr/thredds/catalog/work/YOURLOGIN/catalog.html> for ATLAS and MONITORING

10. About password

ccc_password_expiration helps you to know expiration date of your password. Currently password have to be changed one time per year.

```
> ccc_password_expiration
Password for xxxxx@USERS-CCRT.CCC.CEA.FR: Pppppppppp
Your password will expire in 70 days on Fri Nov 22 08:42:59 2013
> ccc_password_expiration -h
Usage: ccc_password_expiration [username[@realm]]
```

11. The TGCC's machines

11.1. [Irene](#)

See the documentation for [Irene](#). Opened in June 2018.