

Working on the curie machine

Table of Content

Working on the curie machine	1
1. Online users manual	2
2. Job manager commands	2
3. Before starting a job	2
3.1. Specify the project name	2
3.2. QoS test	2
4. Other job manager commands	2
5. Fat nodes / Thin nodes	4
5.1. SSD on standard node : how to use it for rebuild job	4
5.2. RAM on fat node : how to use it for rebuild job	4
6. Job Header for MPI - MPI/OMP with libIGCM	4
6.1. Forced model	4
6.1.1. MPI	4
6.1.2. hybrid MPI-OMP	5
6.2. Coupled model	5
6.2.1. MPI	5
6.2.2. hybrid MPI-OMP	5
7. Tricks	6
8. How to use the ddt debugger for the coupled model (or any other MPMD mode)	6
8.1. MPI only	6
8.2. Hybrid MPI-OpenMP (use of mpirun -rankfile method)	7
9. Errors on curie when running simulations	7
9.1. Job error: KILLED ... WITH SIGNAL 15	7
9.2. Isn't there restart files for LMDZ?	7
9.3. Errors when creating or transferring files	7
9.4. Job error: Segmentation fault	8
9.5. Error when submitting jobs	8
9.6. Long waiting time before a job execution	8
9.7. Disk quota exceeded	8
10. REDO	8
11. Feedback	9
11.1. On November 20th 2012	9
11.2. In June 2012	9
11.3. Error to watch in the post processing: WARNING Intra-file non-monotonicity. Record coordinate "time_counter" does not monotonically increase	9

1. Online users manual

- The command `curie.info` returns all useful information on the curie machine. Keep it in mind and use it often.
- The TGCC's storage spaces are visible from the curie machine: `$HOME` , `$CCCWORKDIR` and `$CCCSTOREDIR`
- The `$SCRATCHDIR` space only exists for the curie machine. Be careful, this space is often cleaned and only files that are less than 40 days are stored.
- You will find the users manual provided by TGCC [here](#) : provide your TGCC/CCRT login and password in the tab for TGCC.

2. Job manager commands

- `ccc_msub mon_job` -> submit a job
- `ccc_mdel ID` -> kill the job with the specified ID number
- `ccc_mstat -u login` -> display all jobs submitted by login
- `ccc_mpp` -> display all jobs submitted on the machine. `ccc_mpp -n` to avoid colors.
- `ccc_mpp -u $(whoami)` -> display your jobs.

3. Before starting a job

3.1. Specify the project name

Since January 2013, you must specify in the header from which project you will use computing time:

```
#MSUB -A genxxx
```

3.2. QoS test

QoS (Quality of Service) is a test queue. You can have a maximum of 2 jobs in test queue, each of them is limited to 30min and 8 nodes (= 256tasks). In the job header you must add:

```
#MSUB -Q test
```

and change the CPU time limit

```
#MSUB -T 1800
```

4. Other job manager commands

- `ccc_mpeek ID` -> display the output listing of a job. Note that the job outputs are visible while the job is running.
- `ccc_mpinfo` to find out about the classes status and about the computing requirements of the associated processors. For example (11/26/2012) :

```
/usr/bin/ccc_mpinfo
-----CPUS-----
PARTITION  STATUS  TOTAL  DOWN  USED  FREE  TOTAL  DOWN  USED  FREE  MpC  CpN  SpN  CpS  TpC
-----
standard   up      80368   32   77083  3253   5023    1   4824   198   4000  16   2   8   1
xlarge     up      10112   128  1546   8438    79    1    14    64   4000 128  16   8   1
hybrid     up      1144    0    264    880    143    0    33   110   2900  8   2   4   1
```

- detail of a running job. One command per line `ccc_mprun` :

```
ccc_mstat -H 375309
JobID  JobName  Partitio ReqCPU          Account          Start  Timelimit  Elapsed  State  ExitCode
-----
375309 v3.histor+ standard    0  gen0826@standard 2012-05-11T16:27:53 1-00:00:00 01:49:03  RUNNING  0:0
375309+ p86maf_ru+ 32  gen0826@standard 2012-05-11T16:28:16                00:14:19  COMPLETED  0:0
```

```

375309+ p86maf_ru+      32  gen0826@standard 2012-05-11T16:42:47      00:12:54  COMPLETED  0:0
375309+ p86maf_ru+      32  gen0826@standard 2012-05-11T16:55:59      00:13:30  COMPLETED  0:0
375309+ p86maf_ru+      32  gen0826@standard 2012-05-11T17:09:31      00:13:22  COMPLETED  0:0
375309+ p86maf_ru+      32  gen0826@standard 2012-05-11T17:24:06      00:13:36  COMPLETED  0:0
375309+ p86maf_ru+      32  gen0826@standard 2012-05-11T17:37:54      00:13:31  COMPLETED  0:0
375309+ p86maf_ru+      32  gen0826@standard 2012-05-11T17:51:28      00:14:19  COMPLETED  0:0
375309+ p86maf_ru+      32  gen0826@standard 2012-05-11T18:05:57      00:10:59  RUNNING    0:0

```

information about the error code of jobs: ccc_macct nqsid

- this job ran successfully:

```

> ccc_macct 698214
Jobid      : 698214
Jobname    : v5.historicalCMR4.452
User       : p86maf
Account    : gen2211@s+
Limits     : time = 1-00:00:00 , memory/task = Unknown
Date       : submit=06/09/2012 17:51:56, start=06/09/2012 17:51:57 , end= 07/09/2012 02:20:28
Execution  : partition = standard , QoS = normal
Resources  : ncpus = 53 , nnodes = 4
            Nodes=curie[2166,5964,6002,6176]

Memory /step
-----
JobID      Max (Node:Task)  AveTask  Virtual (Go)  AveTask
-----
698214     0(               : 0)      0         0.00(          : 0)      0.00
698214.batch 25(curie2166    : 0)      0         0.00(curie2166 : 0)      0.00
698214.0   952(curie2166   : 0)      0         3.00(curie2166 : 1)      0.00
...
698214.23  952(curie2166   : 0)      0         3.00(curie2166 : 2)      0.00

Accounting / step
-----
JobID      JobName  Ncpus Nnodes  Ntasks  Elapsed  State  ExitCode
-----
698214     v5.historic+  53    4        4        08:28:31  COMPLETED  0:0
698214.batch  batch      1     1         1        08:28:31  COMPLETED
698214.0   p86maf_run_+  53    4        53       00:20:53  COMPLETED
698214.1   p86maf_run_+  53    4        53       00:20:20  COMPLETED
...
698214.23  p86maf_run_+  53    4        53       00:21:06  COMPLETED

```

- this job failed with an error code:

```

> ccc_macct 680580
Jobid      : 680580
Jobname    : v5.historicalCMR4
User       : p86maf
Account    : gen2211@s+
Limits     : time = 1-00:00:00 , memory/task = Unknown
Date       : submit=30/08/2012 17:10:06, start=01/09/2012 04:11:30 , end= 01/09/2012 04:42:48
Execution  : partition = standard , QoS = normal
Resources  : ncpus = 53 , nnodes = 5
            Nodes=curie[2097,2107,4970,5413,5855]

Memory /step
-----

```

JobID	Resident (Mo)		AveTask	Virtual (Go)		AveTask
	Max (Node:Task)			Max (Node:Task)		
680580	0(: 0)	0	0.00(: 0)	0.00
680580.batch	28(curie2097	: 0)	0	0.00(curie2097	: 0)	0.00
680580.0	952(curie2097	: 0)	0	3.00(curie2097	: 1)	0.00
680580.1	316(curie2097	: 8)	0	2.00(curie2097	: 8)	0.00

Accounting / step

JobID	JobName	Ncpus	Nnodes	Ntasks	Elapsed	State	ExitCode
680580	v5.historic+	53	5		00:31:18	COMPLETED	0:9
680580.batch	batch	1	1	1	00:31:18	COMPLETED	
680580.0	p86maf_run_+	53	5	53	00:19:48	COMPLETED	
680580.1	p86maf_run_+	53	5	53	00:10:06	CANCELLED	b+

5. Fat nodes / Thin nodes

Fat nodes for the IPSLCM5A-LR coupled model are slower than titane (130%). Thin nodes are two times faster than fat nodes for computations; they are as fast as fat nodes for post processing.

We decided to use thin nodes for computations and fat nodes for post processing. Be careful! Since November 21st 2012, you must use at least libGCM_v2.0_rc1 to perform post processing on fat nodes.

The job header must include #MSUB -q standard to use thin nodes.

The job header must include #MSUB -q xlarge to use fat nodes.

5.1. SSD on standard node : how to use it for rebuild job

SSD usage could accelerate rebuild job. It's very useful for medium and high resolution configuration like IPSLCM5A-MR. You have only to change header and RUN_DIR_PATH in rebuild.job. Take care you will run faster but cost will be multiplied by a factor of 16 because standard node ie 16 cpus are dedicated. Beware of the size of the /tmp (64GB/node) : if you have configuration with very high resolution and very high output frequency, the /tmp of standard node could be too small; in this case see below.

```
#MSUB -q standard # thin nodes
#MSUB -x # exclusive node
RUN_DIR_PATH=/tmp/REBUILD_DIR_MR_$$
```

5.2. RAM on fat node : how to use it for rebuild job

If /tmp of standard node (64GB) is too small for you, you can use fat node. You have to know the /tmp of fat node is also of 64GB. You have to use the RAM disk which is 250GB/node. You have only to change header and RUN_DIR_PATH in rebuild.job. Take care you will run faster but cost will be multiplied by a factor of 128 because fat node ie 128 cpus are dedicated.

```
#MSUB -q xlarge # fat nodes
#MSUB -x # exclusive node
RUN_DIR_PATH=/dev/shm/REBUILD_DIR_MR_$$
```

6. Job Header for MPI - MPI/OMP with libGCM

6.1. Forced model

6.1.1. MPI

To launch a job on XXX MPI tasks

```
#MSUB -r MyJob
#MSUB -o Script_Output_MyJob.000001 # standard output
#MSUB -e Script_Output_MyJob.000001 # error output
#MSUB -eo
#MSUB -n XXX # number of MPI task
#MSUB -T 86400 # Wall clock limit (seconds)
#MSUB -q standard # thin nodes
#MSUB -A gen****
BATCH_NUM_PROC_TOT=$BRIDGE_MSUB_NPROC
```

6.1.2. hybrid MPI-OMP

Hybrid version are only available with _v6 configurations

To launch a job on XXX MPI tasks and YYY threads OMP on each task

- first you need to modify your config.card

```
ATM= (gcm.e, lmdz.x, XXXMPI, YYYOMP)
```

- second you need to modify your job header

```
#MSUB -r MyJob
#MSUB -o Script_Output_MyJob.000001 # standard output
#MSUB -e Script_Output_MyJob.000001 # error output
#MSUB -eo
#MSUB -n XXX # number of MPI task
#MSUB -c YYY # number of threads OMP by task
#MSUB -T 86400 # Wall clock limit (seconds)
#MSUB -q standard # thin nodes
#MSUB -A gen****
BATCH_NUM_PROC_TOT=XXX * YYY # number of MPI task * OMP threads
```

6.2. Coupled model

6.2.1. MPI

To launch a job on XXX MPI tasks

```
#MSUB -r MyCoupledJob
#MSUB -o Script_Output_MyCoupledJob.000001 # standard output
#MSUB -e Script_Output_MyCoupledJob.000001 # error output
#MSUB -eo
#MSUB -n XXX # number of MPI task
#MSUB -T 86400 # Wall clock limit (seconds)
#MSUB -q standard # thin nodes
#MSUB -A gen****
BATCH_NUM_PROC_TOT=$BRIDGE_MSUB_NPROC
```

6.2.2. hybrid MPI-OMP

Hybrid version are only available with _v6 configurations

To launch a job on XXX MPI tasks and YYY threads OMP on each task

- first you need to modify your config.card

```
ATM= (gcm.e, lmdz.x, 24MPI, 2OMP)
SRF= ( " " , " " )
```

```

SBG= ( "" , "" )
OCE= ( opa, opa.xx , 7MPI)
ICE= ( "" , "" )
MBG= ( "" , "" )
CPL= ( "" , "" )
IOS= ( xios_server.exe, xios.x, 1MPI)

```

- second you need to modify your job header

```

#MSUB -r MyCoupledJob
#MSUB -o Script_Output_MyCoupledJob.000001 # standard output
#MSUB -e Script_Output_MyCoupledJob.000001 # error output
#MSUB -eo
#MSUB -n XXX * YYY # Number of cores
#MSUB -N (XXX * YYY) / 16 # Number of nodes (16 cores per node)
#MSUB -x # exclusive node
#MSUB -E '--cpu_bind=none'
#MSUB -T 86400 # Wall clock limit (seconds)
#MSUB -q standard # thin nodes
#MSUB -A gen***

```

7. Tricks

- export LANG=C to correctly display curie.info (by default for new logins)
- use [SHIFT] [CTL] C to copy part of a text displayed by curie.info
- ccc_quota gives usage of HOME, WORK, STORE and SCRATCHDIR. ccc_quota gives also detailed informations about CCCSTOREDIR usage. These informations are updated once a day at 1pm.

8. How to use the ddt debugger for the coupled model (or any other MPMD mode)

8.1. MPI only

- compile the model you wish to debug with the -g option (necessary in order to have access to sources from the ddt interface)
- create a debug directory which includes the model executables and the input files required by the model
- create a simplified debug job which allows you to start a run in the debug directory
- add the command "module load ddt" to your job
- add the creation of configuration run_file
- add a ddt start command in your job
- delete the environment variable SLURM_SPANK_AUKS : unset SLURM_SPANK_AUKS

```

...
module load ddt
unset SLURM_SPANK_AUKS

echo "-np 1 ${DDTPATH}/bin/ddt-client ${TMPDIR_DEBUG}/oasis" > run_file
echo "-np 26 ${DDTPATH}/bin/ddt-client ${TMPDIR_DEBUG}/lmdz.x" >> run_file
echo "-np 5 ${DDTPATH}/bin/ddt-client ${TMPDIR_DEBUG}/opa.xx" >> run_file

ddt

```

- connect yourself to curie in SSH mode with graphic export (option -X) and enter your password (if you have SSH keys on the front-end machine, move the ~/.ssh/authorized_keys* files outside of the directory, disconnect and reconnect yourself)
- start the job with graphic export : ccc_msub -X Job
- when the ddt window appears:
 - click on "Run and Debug a Program"
 - in Application select one of the 3 model executables (which one does not matter)

- in MPI Implementation choose the "OpenMPI (Compatibility)" mode
- in mpirun arguments put "--app \${TMPDIR_DEBUG}/run_file" with TMPDIR_DEBUG = debug directory
- click on "Run" then on the "play" key in the upper left corner

8.2. Hybrid MPI-OpenMP (use of mpirun -rankfile method)

- compile the model you wish to debug with the -g option (necessary in order to have access to sources from the ddt interface)
- create a debug directory which includes the model executables and the input files required by the model
- create a simplified debug job which allows you to start a run in the debug directory
- add the command "module load ddt" to your job
- example with 4 OpenMP threads for lmdz and 1 OpenMP thread for nemo :

```
ddt -start -n 51 -mpiargs "-rankfile rankfile.txt --tag-output \  
-np 20 -x KMP_STACKSIZE=3g -x KMP_LIBRARY=turnaround -x MKL_SERIAL=YES -x OMP_NUM_THREADS=4 ./lmdz.x : \  
-np 31 -x OMP_NUM_THREADS=1 ./opa.xx  
"
```

- start the job with graphic export : ccc_msub -X Job
- if not default option, select "Autoselect Bullx MPI" in Options and relaunch the job.

9. Errors on curie when running simulations

9.1. Job error: KILLED ... WITH SIGNAL 15

```
slurmd[curiel1006]: error: *** STEP 639264.5 KILLED AT 2012-08-01T17:00:29 WITH SIGNAL 15 ***
```

This error message means that the time limit is exceeded. To solve the problem type clean_month, increase the time limit (or decrease PeriodNb) and restart.

9.2. Isn't there restart files for LMDZ?

Problem:

- If the coupled model does not run successfully, the whole chain of commands stops because there is no restart file for LMDZ. Read carefully the out_execution file.

Solution:

- look if a file like *error exists in the Debug subdirectory. It contains clear message errors.
- in the executable directory \$SCRATCHDIR/RUN_DIR/xxxx/IPSLCM5A/xxxx look for the out_execution file. If it contains:

```
srun: First task exited 600s ago  
srun: tasks 0-40,42-45: running  
srun: task 41: exited abnormally  
srun: Terminating job step 438782.1  
slurmd[curiel150]: *** STEP 438782.1 KILLED AT 2012-06-10T18:45:41 WITH SIGNAL 9 ***  
slurmd[curiel151]: *** STEP 438782.1 KILLED AT 2012-06-10T18:45:41 WITH SIGNAL 9 ***  
srun: Job step aborted: Waiting up to 2 seconds for job step to finish.  
slurmd[curiel150]: *** STEP 438782.1 KILLED AT 2012-06-10T18:45:41 WITH SIGNAL 9 ***  
slurmd[curiel151]: *** STEP 438782.1 KILLED AT 2012-06-10T18:45:41 WITH SIGNAL 9 ***
```

don't ask questions! Type clean_month and restart the simulation.

9.3. Errors when creating or transferring files

The file system \$CCCWORKDIR, \$CCCSTOREDIR, \$SCRATCHDIR are delicate. The error messages look like:

```
Input/output error
Cannot send after transport endpoint shutdown
```

Don't ask question and resubmit the job.

9.4. Job error: Segmentation fault

```
/var/spool/slurmd/job637061/slurm_script: line 534: 458 Segmentation fault /bin/ksh -x ${TEMPO_SCRIPT}
```

If you have this kind of message don't ask question and resubmit the job.

9.5. Error when submitting jobs

This message:

```
error: Batch job submission failed: Job violates accounting policy (job submit limit, user's size and/or time limits)
```

means that you have submitted too many jobs (wait for the jobs to end and resubmit), that your headers are not properly written, or that you did not specify on which genci project the computing time must be deducted. The `ccc_mqinfo` command returns the maximum number of jobs (to this day: 300 for 24h-max jobs, 8 for 72h-max jobs and 2 for test jobs (30 min and max 8 nodes)):

```
ccc_mqinfo
Name      Priority  MaxCPUs  MaxNodes  MaxRun  MaxSub  MaxTime
-----
long      18       1024     2         8       3-00:00:00
normal    20              300      1-00:00:00
test      40              8         2       00:30:00
```

9.6. Long waiting time before a job execution

The computation of the users priority is based on 3 cumulated criteria:

- Selected QOS (test or not)
- The fair-share value of the account (computed from the project and/or partner computation share and the previous use)
- Job's age

If your job is far down the waiting list and if you are working on different projects, use the project with the least computing time used.

This computation is not satisfying because we would prefer to encourage long simulations. We are looking for real examples of anormal waiting situations. Please take the time to give us your feedback.

9.7. Disk quota exceeded

Be careful to quotas on /scratch! Monitor them with the command `ccc_quota`. Destroy the temporary directories created by jobs that ended too early and that did not clear the `$SCRATCHDIR/TMPDIR_IGCM` and `$SCRATCHDIR/RUN_DIR` directories. You should have a 20 To quota on curie.

```
> ccc_quota
Disk quotas for user xxxx:

----- VOLUME ----- INODE -----
Filesystem  usage    soft    hard    grace  files    soft    hard    grace
-----
scratch    3.53T    20T     20T     -      42.61k    2M     2M     -
store      -        -        -        -      93.76k    100k    101k    -
work      232.53G  1T      1.1T    -      844.8k    1.5M    1.5M    -
```

10. REDO

Simulations with the IPSLCM5A coupled model are reproducible if you use the same Bands file for LMDZ. See trusting TGCC/curie on this webpage:

■ <http://webservices.ipsl.jussieu.fr/trusting/>

11. Feedback

11.1. On November 20th 2012

The maintenance has noticed and corrected the last two problems.

11.2. In June 2012

The 100-yr simulation of piControl in June 2012 :

- 9% of jobs were resubmitted manually (3/34).
- 0,6 % of the jobs and post processing were resubmitted manually (4/694).

11.3. Error to watch in the post processing: WARNING Intra-file non-monotonicity. Record coordinate "time_counter" does not monotonically increase

- To identify quickly: `grep -i monoton create_ts* | awk -F: '{print $1}' | sort -u`
 - (Command to type in `/${SCRATCHDIR}/IGCM_OUT/${TagName}/${SpaceName}/${ExperimentName}/${JobName}/Out`.
 - For example `/ccc/scratch/cont003/dsm/p25mart/IGCM_OUT/IPSLCM5A/DEVT/lgm/LGMBR03/Out`
- Example :

```
+ IGCM_sys_ncrcat --hst -v lon,lat,plev,time_counter,time_counter_bnds,zg v3.rcp45GHG1_20160101_20161231_HF_histhfNMC.nc
ncrcat: WARNING Intra-file non-monotonicity. Record coordinate "time_counter" does not monotonically increase between (
```

- Check the non monotonic time axis:

```
/ccc/cont003/home/dsm/p86broc/dev_python/is_monotone.py OCE/Analyse/TS_DA/v5.historicalMR3_19800101_19891231_1D_vosaline
False
```

- Solution: rm the TS files created and restart with TimeSeries_Checker