Working on TGCC


Table of Content

Working on TGCC	1
1. TGCC presentation	2
2. TGCC's machines and file systems	2
3. How to install your environment on TGCC	2
4. Project and computing needs	2
5. About file systems	3
5.1. Quotas	3
5.2. CCCSCRATCHDIR	3
5.3. CCCWORKDIR	3
5.4. CCCSTOREDIR	3
5.5. ccc_home command to know directory complete pathname	3
5.6. Storage spaces available from ESGF/THREDDS	4
6. Specific directories for projects	4
7. Specific file systems for CMIP6	4
7.1. GENCMIP6_HOME	4
7.2. GENCMIP6_CCCWORKDIR	5
7.3. GENCMIP6_CCCSTOREDIR	5
7.4. GENCMIP6_SCRATCHDIR	5
8. End-of-job messages	5
9. Simulation outputs	5
10. About password	5
11. The TGCC's machines	5
11.1. Irene	5

1. TGCC presentation

http://www-hpc.cea.fr/en/complexe/tgcc.htm

2. TGCC's machines and file systems



3. How to install your environment on TGCC

- More information on the open-access website: http://www-hpc.cea.fr/en/complexe/tgcc.htm
 Online access to the machines' users manual (you will need a TGCC login and password): https://www-tgcc.ccc.cea.fr/.
- Online access to technical issues and news : https://www-tgcc.ccc.cea.fr/en/news/index.html
- TGCC's machine is <u>Irène</u> (Bull Skylake)
- Note: the \$HOME/.snapshot directory contains hourly, daily, and weekly backups of your \$HOME files.

It is important to take the time to install a comfortable and efficient environment.

We suggest the user to use the igcmg environment (in bash) with a copy of the bashrc in his HOME.

ryyy999@irene: cp ~igcmg/MachineEnvironment/irene/bashrc ~/.bashrc

Additionnaly, you can copy and complete the example of bashrc_irene file to create your favorite environment (alias, module load ...). Don't forget to use it in .bashrc.

ryyy999@irene: cp ~igcmg/MachineEnvironment/irene/bashrc_irene ~/.bashrc_irene ryyy999@irene: vi ~/.bashrc # to point your own .bashrc_irene

WARNING : if you have a ~/.profile file, it's better to remove it to avoid any problem during the execution of a simulation with libIGCM

In this environment is specified:

the path to the compiler tool fcm and to the rebuild tool which recombines output files from a parallel model:

export PATH=\$(ccc_home -u igcmg)/Tools/fcm/bin:\$(ccc_home -u igcmg)/Tools/irene/bin:\$PATH

the load of modules giving access to computing or post processing libraries and tools needed on our platform (done in ccc_home -u igcmg/MachineEnvironment/irene/env_atlas_irene).

4. Project and computing needs

• To find out the computing time used by the projects you are involved in (daily update):

ryyy999@irene: ccc_myproject

When you will create a job you need to specify in the header the project from which you will use computing time:

#MSUB -A genxxx

5. About file systems

5.1. Quotas

To check the available and used storage capacities of HOME, CCCSCRATCHDIR, CCCWORKDIR and CCCSTOREDIR:

ryyy999@irene: ccc_quota

On the Irene machine this command will also return the space used by scratch (a specificity of the Irene machine).

This command has been improved and gives a lot of information : quotas and usage of shared space, type and duration of exception.

5.2. CCCSCRATCHDIR

The \$CCCSCRATCHDIRdirectory is often cleaned and only files that are less than 40 days are stored.

5.3. CCCWORKDIR

The \$CCCWORKDIR directory corresponds to the \$WORKDIR directory on Irene. It is large but its content is not backed up. Don't forget to do a backup (tar) for important directories.

5.4. CCCSTOREDIR

To manipulate the files in /ccc/store a few commands are useful:

```
# Demigrate a list of files on CCCSTOREDIR, see also "ccc_hsm -h"
ccc_hsm get $CCCSTOREDIR/FILE1 $CCCSTOREDIR/FILE2 ...
# Demigrate recursively the files from a CCCSTOREDIR directory, see also "ccc_hsm -h"
ccc_hsm get -r $CCCSTOREDIR/DIRECTORY
# Find out the used space on CCCSTOREDIR
cd $CCCSTOREDIR ; find . -printf "%y %s %p \n" | \
    awk '{ SUM+=$2 } END {print "SUM " SUM/1000000 " Mo " SUM/100000000 " Go" }'
# or use --apparent-size with du :
du -sh --apparent-size
```

5.5. ccc_home command to know directory complete pathname

ccc_home could help you to find directory complete pathname for an other user or for you .

```
-X, --ccchome
                     : print the CCC nfs directory path ($CCCHOMEDIR)
-W, --cccwork
                     : print the CCC work directory path ($CCCWORKDIR)
-A, --cccstore
                     : print the CCC store directory path ($CCCSTOREDIR)
-a, --all
                     : print all paths
-u user
                     : show paths for the specified user instead of the current user
-d datadir
                     : show paths for the specified datadir
-n, --no-env
                     : do not load user env to report paths
-h, --help
                     : display this help and exit
> ccc_home -A -u ryyy999
/ccc/store/cont003/genXXX/ryyy999
```

5.6. Storage spaces available from ESGF/THREDDS

To store a file for the first time on esgf/thredds, you must ask for esgf/thredds write access by mail to the TGCC hotline access : hotline.tgcc@cea.fr.

```
On Irene, files available on $CCCWORKDIR are candidates to be available from ESGF/THREDDS :
* use `thredds_cp`command
* files will be hardlinked here : /ccc/work/cont003/thredds/login
From a server web :
https://vesg.ipsl.upmc.fr/thredds/catalog/work_thredds/catalog.html
```

More information about output data available from ESGF/THREDDS here.

6. Specific directories for projects

Since June 2018 3 differents directories are available for each project. More information soon.

7. Specific file systems for CMIP6

For gencmip6 project, and only for it, 3 more file systems and 4 more directories are available. Phase 1 have been installed in april 2016. Phase 2 and Phase 3 will come later in 2017 and 2018.

To use them, in interactive mode, you have to do: module load datadir/gencmip6.

Since libIGCM_v2.8.1, if you set your project to gencmip6/devcmip6, they are automatically used in place of usual HOME, CCCWORKDIR, CCCSTOREDIR and CCCSCRATCHDIR: module switch dfldatadir dfldatadir/gencmip6 called from libIGCM.

7.1. GENCMIP6_HOME

- 50 TB
- gencmip6 group quota
- · dedicated to sources and scripts
- · strongly recommanded for CMIP6 sources and simulations scripts
- regular snapshot are taken by the system. See \$GENCMIP6_HOME/.snapshot Attention : you need an interactive connexion on a compute node :

```
> ccc_mprun -s -p standard -A devcmip6 -T 1800 -Q test
> cd
> . .bash_login
> cd .snapshot
> ls -l
total 44
drwxr-sr-x. 13 xxx gencmip6 4096 Dec 17 09:47 daily.2017-02-07_0010
drwxr-sr-x. 13 xxx gencmip6 4096 Dec 17 09:47 daily.2017-02-08_0010
...
```

7.2. GENCMIP6_CCCWORKDIR

- 2.5 PB in phase 1, 5 PB in phase 2
- gencmip6 group quota
- dedicated to small output files (ATLAS, MONITORING)
- available through https://esgf.extra.cea.fr following work_thredds
- no backup

7.3. GENCMIP6_CCCSTOREDIR

- 2.5 PB in phase 1, 5 PB in phase 2 and 14 PB on tape in phase 3
- gencmip6 group quota
- dedicated to large (more than 1GB) output files (Output, Analyse)
- available through https://esgf.extra.cea.fr following store_thredds
- linked with HSM (tapes)

7.4. GENCMIP6_SCRATCHDIR

- same file system as GENCMIP6_CCCWORKDIR
- used during batch execution (RUN_DIR) and erased at the end of the execution
- regular cleaning after 40 days

8. End-of-job messages

To receive the end-of-job messages sent by the job itself: end of simulation, error,... you must specify your address in the \$HOME/.forward file.

News in June 2018 : On Irene you have to duplicate a .forward for each project HOME.

9. Simulation outputs

Final simulation outputs are stored in \$CCCSTOREDIR/IGCM_OUT and on \$CCCWORKDIR/IGCM_OUT regarding the ATLAS and MONITORING directories.

The esgf/thredd server on TGCC are available via:

- <u>https://vesg.ipsl.upmc.fr/thredds/catalog/catalog.html</u>, click on store, click on your login or directly :
 <u>https://vesg.ipsl.upmc.fr/thredds/catalog/store/YOURLOGIN/catalog.html</u> and ATM (or an other component) for Analyse files (TS or SE)
- <u>Ihttps://vesg.ipsl.upmc.fr/thredds/catalog/catalog.html</u>, click on work, click on your login or directly :
 <u>Ihttps://vesg.ipsl.upmc.fr/thredds/catalog/work/YOURLOGIN/catalog.html</u> for ATLAS and MONITORING

10. About password

ccc_password_expiration helps you to know expiration date of your password. Currently password have to be changed one time per year.

```
> ccc_password_expiration
Password for xxxxx@USERS-CCRT.CCC.CEA.FR: PPPPPPPPP
Your password will expire in 70 days on Fri Nov 22 08:42:59 2013
> ccc_password_expiration -h
Usage: ccc_password_expiration [username[@realm]]
```

11. The TGCC's machines

11.1. <u>Irene</u>

See the documentation for Irene. Opened in June 2018.